SSH

version 1.1

Typeset in LaTeX from SGML source using the DocBuilder-0.9.8.5 Document System.

Contents

1	SSH Reference Manual					
	1.1	ssh	7			
	1.2	ssh_channel	11			
	1.3	ssh_connection	18			
	1.4	ssh_sftp	22			
	1.5	ssh_sftpd	29			
Index of Modules and Functions						

SSH iii

iv SSH

SSH Reference Manual

Short Summaries

- Erlang Module ssh [page 7] Main API of the SSH application
- Erlang Module ssh_channel [page 11] Generic Ssh Channel Behavior
- Erlang Module **ssh_connection** [page 18] This module provides an API to the ssh connection protocol.
- Erlang Module ssh_sftp [page 22] SFTP client.
- Erlang Module **ssh_sftpd** [page 29] Specifies a channel process to handle a sftp subsystem.

ssh

The following functions are exported:

- close(ConnectionRef) -> ok [page 7] Closes a ssh connection
- connect(Host) -> [page 7] Connect to an ssh server.
- connect(Host, Options) -> [page 7] Connect to an ssh server.
- connect(Host, Port, Options) -> {ok, ssh_connection_ref()} | {error, Reason}
 [page 7] Connect to an ssh server.
- connection_info(ConnectionRef, [Option]) ->[{Option, Value}] [page 8] Retrieves information about a connection.
- daemon(Port) ->
 [page 8] Starts a server listening for SSH connections on the given port.
- daemon(Port, Options) -> [page 8] Starts a server listening for SSH connections on the given port.
- daemon(HostAddress, Port, Options) -> ssh_daemon_ref() [page 8] Starts a server listening for SSH connections on the given port.
- shell(Host) -> [page 9]shell(Host, Option) -> [page 9]

- shell(Host, Port, Option) -> _ [page 9]
- start() -> [page 10] Starts the Ssh application.
- start(Type) -> ok | {error, Reason} [page 10] Starts the Ssh application.
- stop() -> ok
 [page 10] Stops the Ssh application.
- stop_daemon(DaemonRef) -> [page 10] Stops the listener and all connections started by the listener.
- stop_daemon(Address, Port) -> ok [page 10] Stops the listener and all connections started by the listener.
- stop_listener(DaemonRef) -> [page 10] Stops the listener, but leaves existing connections started by the listener up and running.
- stop_listener(Address, Port) -> ok [page 10] Stops the listener, but leaves existing connections started by the listener up and running.

ssh_channel

The following functions are exported:

- call(ChannelRef, Msg) -> [page 11] Makes a synchronous call to a channel.
- call(ChannelRef, Msg, Timeout) -> Reply | {error, Reason} [page 11] Makes a synchronous call to a channel.
- cast(ChannelRef, Msg) -> ok
 [page 11] Sends an asynchronous message to the channel ChannelRef and returns ok.
- enter_loop(State) -> _
 [page 12] Makes an existing process into a ssh_channel process.
- init(Options) -> {ok, State} | {ok, State, Timeout} | {stop, Reason} [page 12] Initiates a ssh_channel process.
- reply(Client, Reply) -> _ [page 12] Send a reply to a client.
- start(SshConnection, ChannelId, ChannelCb, CbInitArgs) -> [page 13] Starts a processes that handles a ssh channel.
- start_link(SshConnection, ChannelId, ChannelCb, CbInitArgs) -> {ok, ChannelRef} | {error, Reason}
 [page 13] Starts a processes that handles a ssh channel.
- CallbackModule:code_change(OldVsn, State, Extra) -> {ok, NewState} [page 13] Converts process state when code is changed.
- CallbackModule:init(Args) -> {ok, State} | {ok, State, Timeout} | {stop, Reason}
 [page 14] Makes necessary initializations and returns the initial channel state if the initializations succeed.

- CallbackModule:handle_call(Msg, From, State) -> Result [page 14] Handles messages sent by calling ssh_channel:call/[2,3]
- CallbackModule:handle_cast(Msg, State) -> Result [page 15] Handles messages sent by calling ssh_channel:cact/2
- CallbackModule:handle_msg(Msg, State) -> {ok, State} | {stop, ChannelId, State}
 [page 15] Handle other messages than ssh connection protocol, call or cast messages sent to the channel.
- CallbackModule:handle_ssh_msg(Msg, State) -> {ok, State} | {stop, ssh_channel_id(), State} [page 15] Handles ssh connection protocol messages.
- CallbackModule:terminate(Reason, State) -> _ [page 17]

ssh_connection

The following functions are exported:

- adjust_window(ConnectionRef, ChannelId, NumOfBytes) -> ok [page 19] Adjusts the ssh flowcontrol window.
- close(ConnectionRef, ChannelId) -> ok [page 19] Sends a close message on the channel ChannelId.
- exec(ConnectionRef, ChannelId, Command, TimeOut) ->
 ssh_request_status()
 [page 19] Will request that the server start the execution of the given command.
- exit_status(ConnectionRef, ChannelId, Status) -> ok [page 20] Sends the exit status of a command to the client.
- reply_request(ConnectionRef, WantReply, Status, CannelId) -> ok [page 20] Send status replies to requests that want such replies.
- send(ConnectionRef, ChannelId, Data) -> [page 20] Sends channel data
- send(ConnectionRef, ChannelId, Data, Timeout) -> [page 20] Sends channel data
- send(ConnectionRef, ChannelId, Type, Data) -> [page 20] Sends channel data
- send(ConnectionRef, Channelld, Type, Data, TimeOut) -> ok | {error, timeout} [page 20] Sends channel data
- send_eof(ConnectionRef, ChannelId) -> ok [page 20] Sends eof on the channel ChannelId.
- session_channel(ConnectionRef, Timeout) -> [page 21] Opens a channel for a ssh session. A session is a remote execution of a program. The program may be a shell, an application, a system command, or some built-in subsystem.
- session_channel(ConnectionRef, InitialWindowSize, MaxPacketSize, Timeout) -> {ok, ssh_channel_id()} | {error, Reason} [page 21] Opens a channel for a ssh session. A session is a remote execution of a program. The program may be a shell, an application, a system command, or some built-in subsystem.

- setenv(ConnectionRef, ChannelId, Var, Value, TimeOut) ->
 ssh_request_status()
 [page 21] Environment variables may be passed to the shell/command to be
 started later.
- shell(ConnectionRef, Channelld) -> ssh_request_status() [page 21] Will request that the user's default shell (typically defined in /etc/passwd in UNIX systems) be started at the other end.
- subsystem(ConnectionRef, ChannelId, Subsystem, Timeout) -> ssh_request_status() [page 21]

ssh_sftp

The following functions are exported:

- start_channel(ConnectionRef) ->
 [page 22] Starts a sftp client
- start_channel(ConnectionRef, Options) -> [page 22] Starts a sftp client
- start_channel(Host, Options) -> [page 22] Starts a sftp client
- start_channel(Host, Port, Options) -> {ok, Pid} | {ok, Pid, ConnectionRef} | {error, Reason}
 [page 22] Starts a sftp client
- stop_channel(ChannelPid) -> ok [page 23] Stops the sftp client channel.
- read_file(ChannelPid, File) -> [page 23] Read a file
- read_file(ChannelPid, File, Timeout) -> {ok, Data} | {error, Reason} [page 23] Read a file
- write_file(ChannelPid, File, Iolist) -> [page 23] Write a file
- write_file(ChannelPid, File, Iolist, Timeout) -> ok | {error, Reason}
 [page 23] Write a file
- list_dir(ChannelPid, Path) ->
 [page 23] List directory
- list_dir(ChannelPid, Path, Timeout) -> {ok, Filenames} | {error, Reason} | [page 23] List directory
- open(ChannelPid, File, Mode) -> [page 23] Open a file and return a handle
- open(ChannelPid, File, Mode, Timeout) -> {ok, Handle} | {error, Reason}
 [page 23] Open a file and return a handle
- opendir(ChannelPid, Path) ->
 [page 24] Open a directory and return a handle

- opendir(ChannelPid, Path, Timeout) -> {ok, Handle} | {error, Reason} [page 24] Open a directory and return a handle
- close(ChannelPid, Handle) -> [page 24] Close an open handle
- close(ChannelPid, Handle, Timeout) -> ok | {error, Reason} [page 24] Close an open handle
- read(ChannelPid, Handle, Len) -> [page 24] Read from an open file
- read(ChannelPid, Handle, Len, Timeout) -> {ok, Data} | eof | {error, Error}
 [page 24] Read from an open file
- pread(ChannelPid, Handle, Position, Len) -> [page 24] Read from an open file
- pread(ChannelPid, Handle, Position, Len, Timeout) -> {ok, Data} |
 eof | {error, Error}
 [page 24] Read from an open file
- aread(ChannelPid, Handle, Len) -> {async, N} | {error, Error} [page 25] Read asynchronously from an open file
- apread(ChannelPid, Handle, Position, Len) -> {async, N} | {error, Error}
 [page 25] Read asynchronously from an open file
- write(ChannelPid, Handle, Data) ->
 [page 25] Write to an open file
- write(ChannelPid, Handle, Data, Timeout) -> ok | {error, Error}
 [page 25] Write to an open file
- pwrite(ChannelPid, Handle, Position, Data) -> ok [page 25] Write to an open file
- pwrite(ChannelPid, Handle, Position, Data, Timeout) -> ok | {error, Error}
 [page 25] Write to an open file
- awrite(ChannelPid, Handle, Data) -> ok | {error, Reason} [page 25] Write asynchronously to an open file
- apwrite(ChannelPid, Handle, Position, Data) -> ok | {error, Reason} [page 25] Write asynchronously to an open file
- position(ChannelPid, Handle, Location) -> [page 26] Seek position in open file
- position(ChannelPid, Handle, Location, Timeout) -> {ok, NewPosition | {error, Error}
 [page 26] Seek position in open file
- read_file_info(ChannelPid, Name) -> [page 26] Get information about a file
- read_file_info(ChannelPid, Name, Timeout) -> {ok, FileInfo} |
 {error, Reason}
 [page 26] Get information about a file
- read_link_info(ChannelPid, Name) -> {ok, FileInfo} | {error, Reason} [page 27] Get information about a symbolic link

```
• read_link_info(ChannelPid, Name, Timeout) -> {ok, FileInfo} |
  {error, Reason}
  [page 27] Get information about a symbolic link
• write_file_info(ChannelPid, Name, Info) ->
  [page 27] Write information for a file
• write_file_info(ChannelPid, Name, Info, Timeout) -> ok | {error,
 Reason}
  [page 27] Write information for a file
• read_link(ChannelPid, Name) ->
  [page 27] Read symbolic link
• read_link(ChannelPid, Name, Timeout) -> {ok, Target} | {error,
 Reason}
  [page 27] Read symbolic link
• make_symlink(ChannelPid, Name, Target) ->
  [page 27] Create symbolic link
• make_symlink(ChannelPid, Name, Target, Timeout) -> ok | {error,
 Reason}
  [page 27] Create symbolic link
• rename(ChannelPid, OldName, NewName) ->
  [page 28] Rename a file
• rename(ChannelPid, OldName, NewName, Timeout) -> ok | {error,
 Reason}
  [page 28] Rename a file
• delete(ChannelPid, Name) ->
  [page 28] Delete a file
• delete(ChannelPid, Name, Timeout) -> ok | {error, Reason}
  [page 28] Delete a file
• make_dir(ChannelPid, Name) ->
  [page 28] Create a directory
• make_dir(ChannelPid, Name, Timeout) -> ok | {error, Reason}
  [page 28] Create a directory
• del_dir(ChannelPid, Name) ->
  [page 28] Delete an empty directory
• del_dir(ChannelPid, Name, Timeout) -> ok | {error, Reason}
  [page 28] Delete an empty directory
```

ssh_sftpd

The following functions are exported:

• subsystem_spec(Options) -> subssystem_spec() [page 29] Returns the subsystem specification that allows an ssh daemon to handle the subsystem "sftp".

SSH Reference Manual ssh

ssh

Erlang Module

Interface module for the SSH application

COMMON DATA TYPES

Type definitions that are used more than once in this module:

```
boolean() = true | false
string() = list of ASCII characters
ssh_daemon_ref() - opaque to the user returned by ssh:daemon/[1,2,3]
ssh_connection_ref() - opaque to the user returned by ssh:connect/[1,2,3]
ip_address() - {N1,N2,N3,N4} % IPv4 | {K1,K2,K3,K4,K5,K6,K7,K8} % IPv6
subsystem_spec() = {subsystem_name(), {channel_callback(), channel_init_args()}}
subsystem_name() = string()
channel_callback() = atom() - Name of the erlang module implementing the subsystem_using the ssh_channel behavior see ssh_channel(3) [page 11]
channel_init_args() = list()
```

Exports

close(ConnectionRef) -> ok

The default is 22, the registered port for SSH.

• Options = [{Option, Value}]

• Port = integer()

ssh SSH Reference Manual

Connects to an SSH server. No channel is started this is done by calling ssh_connect:session_cahnnel/2.

Options are:

- {user_dir, String} Sets the user directory e.i. the directory containing ssh configuration files for the user such as known_hosts, id_rsa, id_dsa and authorized_key. Defaults to the directory normally referd to as ~/.ssh
- {silently_accept_hosts, boolean()} When true hosts are added to the file known_hosts without asking the user. Defaults to false.
- {user_interaction, boolean()} If false disables the client to connect to the server if any user interaction is needed such as accepting that the server will be added to the known_hosts file or supplying a password. Defaults to true. Even if user interaction is allowed it can be suppressed by other options such as silently_accept_hosts and password. Do note that it may not always be desirable to use those options from a security point of view.
- {public_key_alg, ssh_rsa | ssh_dsa} Sets the preferred public key algorithm to use for user authentication. If the the preferred algorithm fails of some reason, the other algorithm is tried. The default is to try ssh_rsa first.
- {connect_timeout, timeout()} Sets a timeout on the transport layer connection. Defaults to infinity.
- {user, String} Provide a user name. If this option is not given, ssh reads from the environment (LOGNAME or USER on unix, USERNAME on Windows).
- {password, string()} Provide a password for password authentication. If this option is not given, the user will be asked for a password if the password authentication method is attempted.
- {user_auth, Fun/3} Provide a fun for password authentication. The fun will be called as fun(User, Password, Opts) and should return true or false.
- {key_cb, atom() = KeyCallbackModule} Provide a special call-back module for key
 handling. The call-back module should be modeled after the ssh_file module.
 The functions that must be exported are: private_host_rsa_key/2,
 private_host_dsa_key/2, lookup_host_key/3 and add_host_key/3. This is
 considered somewhat experimental and will be better documented later on.
- {fd, file_descriptor()} Allow an existing file-descriptor to be used (simply passed on to the transport protocol).

connection_info(ConnectionRef, [Option]) ->[{Option, Value}]

Types:

- Option = client_version | server_version | peer
- Value = term()

Retrieves information about a connection.

SSH Reference Manual ssh

- HostAddress = ip_address() | any
- Options = [{Option, Value}]
- Option = atom()
- Value = term()

Starts a server listening for SSH connections on the given port.

Options are:

- {subsystems, [subsystem_spec()] Provides specifications for handling of
 subsystems. The "sftp" subsystem-spec can be retrived by calling
 ssh_sftd:subsystem_spec/1. If the subsystems option in not present the value of
 [ssh_sftd:subsystem_spec([])] will be used. It is of course possible to set the
 option to the empty list if you do not want the daemon to run any subsystems at
 all.
- {shell, {Module, Function, Args} | fun(string() = User) > pid() | fun(string() = User) Defines the read-eval-print loop used when a shell is requested by the client.
 Example use the erlang shell: {shell, start, []} which is the default behavior.
- {ssh_cli, {channel_callback(), channel_init_args()}} Provide your own cli implementation, e.i. a channel callback module that implements a shell and command execution. Note that you may customize the shell read-eval-print loop using the option shell which is much less work than implementing your own cli channel.
- {system_dir, string()} Sets the system directory, containing the host files that identifies the host for ssh. The default is /etc/ssh, note that SSH normally requires the host files there to be readable only by root.
- {user_passwords, [{string() = User, string() = Password}]} Provide passwords for password authentication. They will be used when someone tries to connect to the server and public key user authentication fails. The option provides a list of valid user names and the corresponding password.
- {password, string()} Provide a global password that will authenticate any user. From a security perspective this option makes the server very vulnerable.
- {pwdfun, fun/2} Provide a function for password validation. This is called with user
 and password as strings, and should return true if the password is valid and false
 otherwise.

```
shell(Host, Option) ->
shell(Host, Port, Option) -> _
```

Types:

- Host = string()
- Port = integer()
- Options see ssh:connect/[1,2,3]

Starts an interactive shell to an SSH server on the given Host. The function waits for user input, and will not return until the remote shell is ended (e.g. on exit from the shell).

SSH Reference Manual ssh

```
start() ->
start(Type) -> ok | {error, Reason}
               Types:
               • Type = permanent | transient | temporary
               • Reason = term()
               Starts the Ssh application. Default type is temporary. See also [application(3)] Requires
               that the crypto application has been started.
stop() \rightarrow ok
               Stops the Ssh application. See also [application(3)]
 stop_daemon(DaemonRef) ->
 stop_daemon(Address, Port) -> ok
               Types:
               • DaemonRef = ssh_daemon_ref()
```

- Address = ip_address()
- Port = integer()

Stops the listener and all connections started by the listener.

```
stop_listener(DaemonRef) ->
stop_listener(Address, Port) -> ok
```

Types:

- DaemonRef = ssh_daemon_ref()
- Address = ip_address()
- Port = integer()

Stops the listener, but leaves existing connections started by the listener up and running.

SSH Reference Manual ssh_channel

ssh_channel

Erlang Module

Ssh services are implemented as channels that are multiplexed over an ssh connection and communicates via the ssh connection protocol. This module provides a callback API that takes care of generic channel aspects such as flow control and close messages and lets the callback functions take care of the service specific parts.

COMMON DATA TYPES

Type definitions that are used more than once in this module and/or abstractions to indicate the intended use of the data type:

```
boolean() = true | false
string() = list of ASCII characters
timeout() = infinity | integer() - in milliseconds.
ssh_connection_ref() - opaque to the user returned by ssh:connect/[1,2,3]
or sent to a ssh channel process
ssh_channel_id() = integer()
ssh_data_type_code() = 1 ("stderr") | 0 ("normal") are currently valid
values see RFC 4254 section 5.2.
```

Exports

```
call(ChannelRef, Msg) ->
call(ChannelRef, Msg, Timeout) -> Reply | {error, Reason}
```

Types:

- ChannelRef = pid()
 As returned by start_link/4
- Msg = term()
- Timeout = timeout()
- Reply = term()
- Reason = closed | timeout

Makes a synchronous call to the channel process by sending a message and waiting until a reply arrives or a timeout occurs. The channel will call CallbackModule:handle_call/3 to handle the message. If the channel process does not exist {error, closed} is returned.

```
cast(ChannelRef, Msg) -> ok
```

ssh_channel SSH Reference Manual

Types:

- ChannelRef = pid()
 As returned by start_link/4
- Msg = term()

Sends an asynchronous message to the channel process and returns ok immediately, ignoring if the destination node or channel process does not exist. The channel will call CallbackModule:handle_cast/2 to handle the message.

enter_loop(State) -> _

Types:

• State = term() - as returned by ssh_channel:init/1

Makes an existing process into a ssh_channel process. Does not return, instead the calling process will enter the ssh_channel process receive loop and become a ssh_channel process. The process must have been started using one of the start functions in proc_lib, see [proc_lib(3)]. The user is responsible for any initialization of the process and needs to call ssh_channel:init/1.

```
init(Options) -> {ok, State} | {ok, State, Timeout} | {stop, Reason}
```

Types:

• Options = [{Option, Value}]

The following options must be present:

```
{channel_cb, atom()} The module that implements the channel behavior.
{init_args(), list()} The list of arguments to the callback modules init function.
{cm, connection_ref()} Reference to the ssh connection.
{channel_id, channel_id()} Id of the ssh channel.
```

Note:

This function is normally not called by the user, it is only needed if for some reason the channel process needs to be started with help of proclib instead calling ssh_channel:start/4 or ssh_channel:startlink/4

```
reply(Client, Reply) -> _
```

Types:

- Client opaque to the user, see explanation below
- Reply = term()

This function can be used by a channel to explicitly send a reply to a client that called call/[2,3] when the reply cannot be defined in the return value of CallbackModule:handle_call/3.

Client must be the From argument provided to the callback function handle_call/3. Reply is an arbitrary term, which will be given back to the client as the return value of ssh_channel:call/[2,3].

SSH Reference Manual ssh_channel

Types:

- SshConnection = ssh_connection_ref()
- ChannelId = ssh_channel_id()
 As returned by ssh_connection:session_channel/[2,4]
- ChannelCb = atom()
 The name of the module implementing the service specific parts of the channel.
- CbInitArgs = [term()]
 Argument list for the init function in the callback module.
- ChannelRef = pid()

Starts a processes that handles a ssh channel. Will be called internally by the ssh daemon or explicitly by the ssh client implementations. A channel process traps exit signals by default.

CALLBACK FUNCTIONS

The functions init/1, terminate/2, handle_ssh_msg/2 and handle_msg/2 are the functions that are required to provide the implementation for a server side channel, such as a ssh subsystem channel that can be plugged into the erlang ssh daemon see ssh:daemon/[2, 3] [page 7]. The handle_call/3, handle_cast/2 code_change/3 and enter_loop/1 functions are only relevant when implementing a client side channel.

CALLBACK TIMEOUTS

If an integer timeout value is provided in a return value of one of the callback functions, a timeout will occur unless a message is received within Timeout milliseconds. A timeout is represented by the atom timeout which should be handled by the handle_msg/2 [page ??] callback function. The atom infinity can be used to wait indefinitely, this is the default value.

Exports

CallbackModule:code_change(OldVsn, State, Extra) -> {ok, NewState}

Types:

• Converts process state when code is changed.

ssh_channel SSH Reference Manual

This function is called by a client side channel when it should update its internal state during a release upgrade/downgrade, i.e. when the instruction {update,Module,Change,...} where Change={advanced,Extra} is given in the appup file. See [OTP Design Principles] for more information. Any new connection will benefit from a server side upgrade but already started connections on the server side will not be affected.

Note:

If there are long lived ssh connections and more than one upgrade in a short time this may cause the old connections to fail as only two versions of the code may be loaded simultaneously.

In the case of an upgrade, OldVsn is Vsn, and in the case of a downgrade, OldVsn is {down, Vsn}. Vsn is defined by the vsn attribute(s) of the old version of the callback module Module. If no such attribute is defined, the version is the checksum of the BEAM file.

State is the internal state of the channel.

Extra is passed as-is from the {advanced, Extra} part of the update instruction.

The function should return the updated internal state.

CallbackModule:init(Args) -> {ok, State} | {ok, State, Timeout} | {stop, Reason}

Types:

- Args = term()
 Last argument to ssh_channel:start_link/4.
- State = term()
- Timeout = timeout()
- Reason = term()

Makes necessary initializations and returns the initial channel state if the initializations succeed.

For more detailed information on timeouts see the section CALLBACK TIMEOUTS [page ??].

CallbackModule:handle_call(Msg, From, State) -> Result

Types:

- Msg = term()
- From = opaque to the user should be used as argument to ssh_channel:reply/2
- State = term()
- Result = {reply, Reply, NewState} | {reply, Reply, NewState, Timeout} | {noreply, NewState} | {noreply , NewState, Timeout} | {stop, Reason, Reply, NewState} | {stop, Reason, NewState}
- Reply = term() will be the return value of ssh_channel:call/[2,3]
- Timeout = timeout()
- NewState = term() a possible updated version of State
- Reason = term()

SSH Reference Manual ssh_channel

Handles messages sent by calling ssh_channel:call/[2,3]

For more detailed information on timeouts see the section CALLBACK TIMEOUTS [page ??].

CallbackModule:handle_cast(Msg, State) -> Result

Types:

- Msg = term()
- State = term()
- Result = {noreply, NewState} | {noreply, NewState, Timeout} | {stop, Reason, NewState}
- NewState = term() a possible updated version of State
- Timeout = timeout()
- Reason = term()

Handles messages sent by calling ssh_channel:cast/2

For more detailed information on timeouts see the section CALLBACK TIMEOUTS [page ??].

CallbackModule:handle_msg(Msg, State) -> {ok, State} | {stop, ChannelId, State}

Types:

- Msg = timeout | term()
- State = term()

Handle other messages than ssh connection protocol, call or cast messages sent to the channel.

Possible erlang 'EXIT'-messages should be handled by this function and all channels should handle the following message.

{ssh_channel_up, ssh_channel_id(), ssh_connection_ref()} This is the first messages that will be received by the channel, it is sent just before the ssh_channel:init/1 function returns successfully. This is especially useful if the server wants to send a message to the client without first receiving a message from the client. If the message is not useful for your particular problem just ignore it by immediately returning {ok, State}.

Types:

- Msg = {ssh_cm, ssh_connection_ref(), SshMsg}
- SshMsg = tuple() see message list below
- State = term()

Handles ssh connection protocol messages that may need service specific attention.

All channels should handle the following messages. For channels implementing subsystems the handle_ssh_msg-callback will not be called for any other messages.

{ssh_cm, ssh_connection_ref(), {data, ssh_channel_id(), ssh_data_type_code(), binary() =
 Data has arrived on the channel. When the callback for this message returns the
 channel behavior will adjust the ssh flow control window.

- {ssh_cm, ssh_connection_ref(), {eof, ssh_channel_id()}} Indicteas that the
 other side will not send any more data.
- {ssh_cm, ssh_connection_ref(), {signal, ssh_channel_id(), ssh_signal()}}
 A signal can be delivered to the remote process/service using the following
 message. Some systems may not implement signals, in which case they should
 ignore this message.
- {ssh_cm, ssh_connection_ref(), {exit_signal, ssh_channel_id(), string() = exit_signal, string A remote execution may terminate violently due to a signal then this message may be received. For details on valid string values see RFC 4254 section 6.10
- {ssh_cm, ssh_connection_ref(), {exit_status, ssh_channel_id(), integer() = ExitStatus}} When the command running at the other end terminates, the following message can be sent to return the exit status of the command. A zero 'exit_status' usually means that the command terminated successfully.

Channels implementing a shell and command execution on the server side should also handle the following messages.

- {ssh_cm, ssh_connection_ref(), {env, ssh_channel_id(), boolean() = WantReply, string() = Van Environment variables may be passed to the shell/command to be started later. Note that before the callback returns it should call the function ssh_connection:reply_request/4 with the boolean value of WantReply as the second argument.
- {ssh_cm, ConnectionRef, {exec, ssh_channel_id(), boolean() = WantReply, string() = Cmd}}
 This message will request that the server start the execution of the given
 command. Note that before the callback returns it should call the function
 ssh_connection:reply_request/4 with the boolean value of WantReply as the
 second argument.
- {ssh_cm, ssh_connection_ref(), {pty, ssh_channel_id(), boolean() = WantReply, {string() = Text A pseudo-terminal has been requested for the session. Terminal is the value of the TERM environment variable value (e.g., vt100). Zero dimension parameters must be ignored. The character/row dimensions override the pixel dimensions (when nonzero). Pixel dimensions refer to the drawable area of the window. The Opcode in the TerminalModes list is the mnemonic name, represented as an lowercase erlang atom, defined in RFC 4254 section 8, or the opcode if the mnemonic name is not listed in the RFC. Example OP code: 53, mnemonic name ECHO erlang atom: echo. Note that before the callback returns it should call the function ssh_connection:reply_request/4 with the boolean value of WantReply as the second argument.
- {ssh_cm, ConnectionRef, {shell, boolean() = WantReply}} This message will
 request that the user's default shell be started at the other end. Note that before
 the callback returns it should call the function ssh_connection:reply_request/4 with
 the value of WantReply as the second argument.
- {ssh_cm, ssh_connection_ref(), {window_change, ssh_channel_id(), integer() = CharWidth, int
 When the window (terminal) size changes on the client side, it MAY send a
 message to the other side to inform it of the new dimensions.

The following message is completely taken care of by the ssh channel behavior

{ssh_cm, ssh_connection_ref(), {closed, ssh_channel_id()}} The channel behavior will send a close message to the other side if such a message has not already been sent and then terminate the channel with reason normal.

SSH Reference Manual ssh_channel

CallbackModule:terminate(Reason, State) -> _

Types:

- Reason = term()
- State = term()

This function is called by a channel process when it is about to terminate. Before this function is called ssh_connection:close/2 will be called if it has not been called earlier. This function should be the opposite of CallbackModule:init/1 and do any necessary cleaning up. When it returns, the channel process terminates with reason Reason. The return value is ignored.

ssh_connection

Erlang Module

This module provides an API to the ssh connection protocol. Not all features of the connection protocol are officially supported yet. Only the ones supported are documented here.

COMMON DATA TYPES

Type definitions that are used more than once in this module and/or abstractions to indicate the intended use of the data type:

```
boolean() = true | false
string() = list of ASCII characters
timeout() = infinity | integer() - in milliseconds.
ssh_connection_ref() - opaque to the user returned by ssh:connect/[1,2,3]
or sent to a ssh channel processes
ssh_channel_id() = integer()
ssh_data_type_code() = 1 ("stderr") | 0 ("normal") are currently valid
values see RFC 4254 section 5.2.
ssh_request_status() = success | failure
```

MESSAGES SENT TO CHANNEL PROCESSES

As a result of the ssh connection protocol messages on the form {ssh_cm, ssh_connection_ref(), term()} will be sent to a channel process. The term will contain information regarding the ssh connection protocol event, for details see the ssh channel behavior callback handle_ssh_msg/2 [page 11]

SSH Reference Manual ssh_connection

Exports

adjust_window(ConnectionRef, ChannelId, NumOfBytes) -> ok

Types:

- ConnectionRef = ssh_connection_ref()
- ChannelId = ssh_channel_id()
- NumOfBytes = integer()

Adjusts the ssh flowcontrol window.

Note:

This will be taken care of by the ssh_channel behavior when the callback handle_ssh_msg/2 [page 11] has returned after processing a {ssh_cm, ssh_connection_ref(), {data, ssh_channel_id(), ssh_data_type_code(), binary()}} message, and should normally not be called explicitly.

close(ConnectionRef, ChannelId) -> ok

Types:

- ConnectionRef = ssh_connection_ref()
- ChannelId = ssh_channel_id()

Sends a close message on the channel ChannelId

Note:

This function will be called by the ssh channel behavior when the channel is terminated see ssh_channel(3) [page 11] and should normally not be called explicitly.

exec(ConnectionRef, ChannelId, Command, TimeOut) -> ssh_request_status()

Types:

- ConnectionRef = ssh_connection_ref()
- ChannelId = ssh_channel_id()
- Command = string()
- Timeout = timeout()

Will request that the server start the execution of the given command, the result will be received as:

- N X {ssh_cm, ssh_connection_ref(), {data, ssh_channel_id(), ssh_data_type_code(), binar The result of executing the command may be only one line or thousands of lines depending on the command.
- 1 X {ssh_cm, ssh_connection_ref(), {eof, ssh_channel_id()}} Indicates that no more data will be sent.

- 0 or 1 X {ssh_cm, ssh_connection_ref(), {exit_signal, ssh_channel_id(), string() = ExitSigna
 Not all systems send signals. For details on valid string values see RFC 4254 section
 6.10
- 0 or 1 X {ssh_cm, ssh_connection_ref(), {exit_status, ssh_channel_id(), integer() = ExitStat
 It is recommended by the ssh connection protocol that this message shall be
 sent, but that may not always be the case.
- 1 X {ssh_cm, ssh_connection_ref(), {closed, ssh_channel_id()}} Indicates that the ssh channel started for the execution of the command has now been shutdown.

These message should be handled by the client. The ssh channel behavior [page 11] can be used when writing a client.

exit_status(ConnectionRef, ChannelId, Status) -> ok

Types:

- ConnectionRef = ssh_connection_ref()
- ChannelId = ssh_channel_id()
- Status = integer()

Sends the exit status of a command to the client.

reply_request(ConnectionRef, WantReply, Status, CannelId) -> ok

Types:

- ConnectionRef = ssh_connection_ref()
- WantReply = boolean()
- Status = ssh_request_status()
- ChannelId = ssh_channel_id()

Sends status replies to requests where the requester has stated that they want a status report e.i. WantReply = true, if WantReply is false calling this function will be a "noop". Should be called after handling an ssh connection protocol message containing a WantReply boolean value. See the ssh_channel behavior callback handle_ssh_msg/2 [page 11]

```
send(ConnectionRef, ChannelId, Data) ->
send(ConnectionRef, ChannelId, Data, Timeout) ->
send(ConnectionRef, ChannelId, Type, Data) ->
send(ConnectionRef, ChannelId, Type, Data, TimeOut) -> ok | {error, timeout}
```

Types:

- ConnectionRef = ssh_connection_ref()
- ChannelId = ssh_channel_id()
- Data = binary()
- Type = ssh_data_type_code()
- Timeout = timeout()

Sends channel data.

```
{\tt send\_eof(ConnectionRef,\ ChannelId)\ ->\ ok}
```

Types:

SSH Reference Manual ssh_connection

- ConnectionRef = ssh_connection_ref()
- ChannelId = ssh_channel_id()

Sends eof on the channel Channelld.

Types:

- ConnectionRef = ssh_connection_ref()
- InitialWindowSize = integer()
- MaxPacketSize = integer()
- Timeout = timeout()
- Reason = term()

Opens a channel for a ssh session. A session is a remote execution of a program. The program may be a shell, an application, a system command, or some built-in subsystem.

setenv(ConnectionRef, ChannelId, Var, Value, TimeOut) -> ssh_request_status()

Types:

- ConnectionRef = ssh_connection_ref()
- ChannelId = ssh_channel_id()
- Var = string()
- Value = string()
- Timeout = timeout()

Environment variables may be passed to the shell/command to be started later.

shell(ConnectionRef, ChannelId) -> ssh_request_status()

Types:

- ConnectionRef = ssh_connection_ref()
- ChannelId = ssh_channel_id()

Will request that the user's default shell (typically defined in /etc/passwd in UNIX systems) be started at the other end.

subsystem(ConnectionRef, ChannelId, Subsystem, Timeout) -> ssh_request_status()

Types:

- ConnectionRef = ssh_connection_ref()
- ChannelId = ssh_channel_id()
- Subsystem = string()
- Timeout = timeout()

Sends a request to execute a predefined subsystem.

ssh_sftp SSH Reference Manual

ssh_sftp

Erlang Module

This module implements an SFTP (SSH FTP) client. SFTP is a secure, encrypted file transfer service available for SSH.

COMMON DATA TYPES

Type definitions that are used more than once in this module and/or abstractions to indicate the intended use of the data type:

```
ssh_connection_ref() - opaque to the user returned by ssh:connect/[1,2,3]
timeout() = infinity | integer() - in milliseconds.
```

TIMEOUTS

If the request functions for the sftp channel return {error, timeout} it does not mean that the request did not reach the server and was not performed, it only means that we did not receive an answer from the server within the time that was expected.

Exports

Types:

- Host = string()
- ConnectionRef = ssh_connection_ref()
- Port = integer()
- Options = [{Option, Value}]
- Reason = term()

If not provided, setups a ssh connection in this case a connection reference will be returned too. A ssh channel process is started to handle the communication with the SFTP server, the returned pid for this process should be used as input to all other API functions in this module.

Options are:

SSH Reference Manual ssh_sftp

{timeout, timeout()} The timeout is passed to the ssh_channel start function, and defaults to infinity.

All other options are directly passed to ssh:connect[2/3] [page 7] or ignored if a connection is already provided.

stop_channel(ChannelPid) -> ok

Types:

ChannelPid = pid()

Stops a sftp channel. If the ssh connection should be closed call ssh:close/1 [page 7].

```
read_file(ChannelPid, File) ->
read_file(ChannelPid, File, Timeout) -> {ok, Data} | {error, Reason}
```

Types:

- ChannelPid = pid()
- File = string()
- Data = binary()
- Timeout = timeout()
- Reason = term()

Reads a file from the server, and returns the data in a binary, like file:read_file/1.

```
write_file(ChannelPid, File, Iolist) ->
write_file(ChannelPid, File, Iolist, Timeout) -> ok | {error, Reason}
```

Types:

- ChannelPid = pid()
- File = string()
- Data = binary()
- Timeout = timeout()
- Reason = term()

Writes a file to the server, like file:write_file/2. The file is created if it's not there.

```
list_dir(ChannelPid, Path) ->
list_dir(ChannelPid, Path, Timeout) -> {ok, Filenames} | {error, Reason}
```

Types:

- ChannelPid = pid()
- Path = string()
- Filenames = [Filename]
- Filename = string()
- Timeout = timeout()
- Reason = term()

Lists the given directory on the server, returning the filenames as a list of strings.

```
open(ChannelPid, File, Mode) ->
open(ChannelPid, File, Mode, Timeout) -> {ok, Handle} | {error, Reason}
```

ssh_sftp SSH Reference Manual

Types:

- ChannelPid = pid()
- File = string()
- Mode = [Modeflag]
- Modeflag = read | write | creat | trunc | append | binary
- Timeout = timeout()
- Handle = term()
- Reason = term()

Opens a file on the server, and returns a handle that is used for reading or writing.

```
opendir(ChannelPid, Path) -> opendir(ChannelPid, Path, Timeout) -> \{ok, Handle\} \mid \{error, Reason\}
```

Types:

- ChannelPid = pid()
- Path = string()
- Timeout = timeout()
- Reason = term()

Opens a handle to a directory on the server, the handle is used for reading directory contents.

```
\label{loss} $$ \close(ChannelPid, Handle) -> $$ \close(ChannelPid, Handle, Timeout) -> ok \mid \{error, Reason\} $$
```

Types:

- ChannelPid = pid()
- Handle = term()
- Timeout = timeout()
- Reason = term()

Closes a handle to an open file or directory on the server.

Types:

- ChannelPid = pid()
- Handle = term()
- Position = integer()
- Len = integer()
- Timeout = timeout()
- Data = string() | binary()
- Reason = term()

SSH Reference Manual ssh_sftp

Reads Len bytes from the file referenced by Handle. Returns {ok, Data}, or eof, or {error, Reason}. If the file is opened with binary, Data is a binary, otherwise it is a string.

If the file is read past eof, only the remaining bytes will be read and returned. If no bytes are read, eof is returned.

The pread function reads from a specified position, combining the position and read functions.

```
aread(ChannelPid, Handle, Len) -> {async, N} | {error, Error}
apread(ChannelPid, Handle, Position, Len) -> {async, N} | {error, Error}
```

Types:

- ChannelPid = pid()
- Handle = term()
- Position = integer()
- Len = integer()
- N = term()
- Reason = term()

Reads from an open file, without waiting for the result. If the handle is valid, the function returns $\{async, N\}$, where N is a term guaranteed to be unique between calls of aread. The actual data is sent as a message to the calling process. This message has the form $\{async_reply, N, Result\}$, where Result is the result from the read, either $\{ok, Data\}$, or eof, or $\{error, Error\}$.

The apread function reads from a specified position, combining the position and aread functions.

```
write(ChannelPid, Handle, Data) ->
write(ChannelPid, Handle, Data, Timeout) -> ok | {error, Error}
pwrite(ChannelPid, Handle, Position, Data) -> ok
pwrite(ChannelPid, Handle, Position, Data, Timeout) -> ok | {error, Error}
```

Types:

- ChannelPid = pid()
- Handle = term()
- Position = integer()
- Data = iolist()
- Timeout = timeout()
- Reason = term()

Write data to the file referenced by Handle. The file should be opened with write or append flag. Returns ok if successful and {error, Reason} otherwise.

Typical error reasons are:

ebadf The file is not opened for writing. enospc There is a no space left on the device.

```
awrite(ChannelPid, Handle, Data) -> ok | {error, Reason}
apwrite(ChannelPid, Handle, Position, Data) -> ok | {error, Reason}
```

ssh_sftp SSH Reference Manual

Types:

- ChannelPid = pid()
- Handle = term()
- Position = integer()
- Len = integer()
- Data = binary()
- Timeout = timeout()
- Reason = term()

Writes to an open file, without waiting for the result. If the handle is valid, the function returns {async, N}, where N is a term guaranteed to be unique between calls of awrite. The result of the write operation is sent as a message to the calling process. This message has the form {async_reply, N, Result}, where Result is the result from the write, either ok, or {error}.

The apwrite writes on a specified position, combining the position and awrite operations.

```
position(ChannelPid, Handle, Location) ->
position(ChannelPid, Handle, Location, Timeout) -> {ok, NewPosition | {error, Error}
```

Types:

- ChannelPid = pid()
- Handle = term()
- Location = Offset | {bof, Offset} | {cur, Offset} | {eof, Offset} | bof | cur | eof
- Offset = int()
- Timeout = timeout()
- NewPosition = integer()
- Reason = term()

Sets the file position of the file referenced by Handle. Returns {ok, NewPosition (as an absolute offset) if successful, otherwise {error, Reason}. Location is one of the following:

```
Offset The same as {bof, Offset}.
{bof, Offset} Absolute offset.
{cur, Offset} Offset from the current position.
{eof, Offset} Offset from the end of file.
bof | cur | eof The same as above with Offset 0.
```

```
read_file_info(ChannelPid, Name) ->
read_file_info(ChannelPid, Name, Timeout) -> {ok, FileInfo} | {error, Reason}
```

Types

- ChannelPid = pid()
- Name = string()
- Handle = term()
- Timeout = timeout()
- FileInfo = record()
- Reason = term()

SSH Reference Manual ssh_sftp

Returns a file_info record from the file specified by Name or Handle, like file:read_file_info/2.

read_link_info(ChannelPid, Name) -> {ok, FileInfo} | {error, Reason}
read_link_info(ChannelPid, Name, Timeout) -> {ok, FileInfo} | {error, Reason}

Types:

- ChannelPid = pid()
- Name = string()
- Handle = term()
- Timeout = timeout()
- FileInfo = record()
- Reason = term()

Returns a file_info record from the symbolic link specified by Name or Handle, like file:read_link_info/2.

```
write_file_info(ChannelPid, Name, Info) ->
write_file_info(ChannelPid, Name, Info, Timeout) -> ok | {error, Reason}
```

Types:

- ChannelPid = pid()
- Name = string()
- Info = record()
- Timeout = timeout()
- Reason = term()

Writes file information from a file_info record to the file specified by Name, like file:write_file_info.

```
read_link(ChannelPid, Name) ->
read_link(ChannelPid, Name, Timeout) -> {ok, Target} | {error, Reason}
```

Types:

- ChannelPid = pid()
- Name = string()
- Target = string()
- Reason = term()

Read the link target from the symbolic link specified by name, like file:read_link/1.

```
make_symlink(ChannelPid, Name, Target) ->
make_symlink(ChannelPid, Name, Target, Timeout) -> ok | {error, Reason}
```

Types:

- ChannelPid = pid()
- Name = string()
- Target = string()
- Reason = term()

Creates a symbolic link pointing to Target with the name Name, like file:make_symlink/2.

ssh_sftp SSH Reference Manual

```
rename(ChannelPid, OldName, NewName) ->
rename(ChannelPid, OldName, NewName, Timeout) -> ok | {error, Reason}
              Types:
              • ChannelPid = pid()
              • OldName = string()
              • NewName = string()
              • Timeout = timeout()
              • Reason = term()
              Renames a file named OldName, and gives it the name NewName, like file:rename/2
delete(ChannelPid, Name) ->
delete(ChannelPid, Name, Timeout) -> ok | {error, Reason}
              Types:
              ChannelPid = pid()
              Name = string()
              • Timeout = timeout()
              • Reason = term()
              Deletes the file specified by Name, like file:delete/1
make_dir(ChannelPid, Name) ->
make_dir(ChannelPid, Name, Timeout) -> ok | {error, Reason}
              Types:
              • ChannelPid = pid()
              • Name = string()
              • Timeout = timeout()
              • Reason = term()
              Creates a directory specified by Name. Name should be a full path to a new directory.
              The directory can only be created in an existing directory.
```

```
del_dir(ChannelPid, Name) ->
del_dir(ChannelPid, Name, Timeout) -> ok | {error, Reason}
```

Types:

- ChannelPid = pid()
- Name = string()
- Timeout = timeout()
- Reason = term()

Deletes a directory specified by Name. The directory should be empty.

SSH Reference Manual ssh_sftpd

ssh_sftpd

Erlang Module

Specifies a channel process to handle a sftp subsystem.

COMMON DATA TYPES

```
subsystem_spec() = {subsystem_name(), {channel_callback(),
    channel_init_args()}}
subsystem_name() = "sftp"
channel_callback() = atom() - Name of the erlang module implementing the
subsystem using the ssh_channel behavior see ssh_channel(3) [page 11]
    channel_init_args() = list() - The one given as argument to function
subssystem_spec/1.
```

Exports

```
subsystem_spec(Options) -> subssystem_spec()
```

Types:

• Options = [{Option, Value}]

Should be used together with ssh:daemon/[1,2,3]

Options are:

{cwd, String} Sets the initial current working directory for the server.

- {file_handler, CallbackModule} Determines which module to call for communicating with the file server. Default value is ssh_sftpd_file that uses the file and filelib API:s to access the standard OTP file server. This option may be used to plug in the use of other file servers.
- {max_files, Integer} The default value is 0, which means that there is no upper limit. If supplied, the number of filenames returned to the sftp client per READDIR request, is limited to at most the given value.
- {root, String} Sets the sftp root directory. The user will then not be able to see any
 files above this root. If for instance the root is set to /tmp the user will see this
 directory as / and if the user does cd /etc the user will end up in /tmp/etc.

ssh_sftpd SSH Reference Manual

Index of Modules and Functions

Modules are typed in *this way*. Functions are typed in this way.

```
ssh_connection, 19
adjust_window/3
    ssh_connection, 19
                                                       ssh_sftp, 24
apread/4
                                                   close/3
    ssh_sftp, 25
                                                       ssh_sftp, 24
apwrite/4
                                                   connect/1
                                                       ssh . 7
    ssh_sftp, 25
aread/3
                                                   connect/2
    ssh_sftp, 25
                                                       ssh, 7
awrite/3
                                                   connect/3
    ssh_sftp, 25
                                                       ssh, 7
                                                   connection_info/2
cal1/2
                                                       ssh , 8
    ssh_channel, 11
call/3
                                                   daemon/1
    ssh_channel, 11
                                                       ssh, 8
CallbackModule:code_change/3
                                                   daemon/2
    ssh_channel, 13
                                                       ssh, 8
CallbackModule:handle_call/3
                                                   daemon/3
    ssh_channel, 14
                                                       ssh, 8
CallbackModule:handle_cast/2
                                                   del_dir/2
    ssh_channel, 15
                                                       ssh_sftp, 28
CallbackModule:handle_msg/2
                                                   del_dir/3
    ssh_channel, 15
                                                       ssh_sftp, 28
CallbackModule:handle_ssh_msg/2
                                                   delete/2
    ssh_channel, 15
                                                       ssh_sftp, 28
CallbackModule:init/1
                                                   delete/3
    ssh_channel . 14
                                                       ssh_sftp, 28
CallbackModule:terminate/2
    ssh_channel, 17
                                                   enter_loop/1
                                                       ssh_channel, 12
cast/2
                                                   exec/4
    ssh_channel, 11
                                                       ssh_connection, 19
close/1
    ssh, 7
                                                   exit_status/3
                                                       ssh_connection, 20
close/2
```

init/1 ssh_channel, 12	read_file/3 ssh_sftp, 23
list_dir/2	read_file_info/2 ssh_sftp, 26
ssh_sftp, 23 list_dir/3	read_file_info/3 ssh_sftp, 26
ssh_sftp , 23	read_link/2 ssh_sftp, 27
make_dir/2 ssh_sftp, 28	read_link/3 ssh_sftp, 27
make_dir/3 ssh_sftp, 28	read_link_info/2 ssh_sftp, 27
make_symlink/3 ssh_sftp, 27	read_link_info/3 ssh_sftp, 27
make_symlink/4 ssh_sftp, 27	rename/3 ssh_sftp, 28
open/3 ssh_sftp, 23	rename/4 ssh_sftp, 28
open/4 ssh_sftp, 23	reply/2 ssh_channel, 12
opendir/2 ssh_sftp, 24	reply_request/4 ssh_connection, 20
opendir/3 ssh_sftp, 24	send/3 ssh_connection, 20
position/3 ssh_sftp, 26	send/4 ssh_connection, 20
position/4 ssh_sftp, 26	send/5 ssh_connection, 20
pread/4 ssh_sftp, 24	send_eof/2 ssh_connection, 20
pread/5 ssh_sftp, 24	session_channe1/2 ssh_connection, 21
pwrite/4 ssh_sftp, 25	session_channe1/4 ssh_connection, 21
pwrite/5 ssh_sftp, 25	setenv/5 ssh_connection , 21
read/3	shell/1 ssh , 9
ssh_sftp , 24 read/4 ssh_sftp , 24	shell/2 ssh, 9 ssh_connection, 21
read_file/2 ssh_sftp, 23	shell/3 ssh, 9

ssh			apread/4, 25
c	close/1, 7		apwrite/4, 25
c	connect/1, 7		aread/3, 25
C	connect/2, 7		awrite/3, 25
C	connect/3, 7		close/2, 24
C	connection_info/2,8		close/3, 24
	laemon/1, 8		del_dir/2, 28
d	laemon/2, 8		del_dir/3, 28
	laemon/3, 8		delete/2, 28
	hell/1, 9		delete/3, 28
	shell/2, 9		list_dir/2,23
	shell/3, 9		list_dir/3,23
	start/0, 10		make_dir/2, 28
	tart/1, 10		make_dir/3, 28
	stop/0, 10		make_symlink/3,27
	top_daemon/1, 10		make_symlink/4, 27
	top_daemon/2, 10		open/3, 23
	top_listener/1, 10		open/4, 23
	top_listener/2, 10		opendir/2, 24
	_		opendir/3, 24
	hannel		position/3, 26
C	all/2, 11		position/4, 26
C	all/3, 11		pread/4, 24
C	SallbackModule:code_change/3,13		pread/5, 24
C	SallbackModule:handle_call/3, 14		pwrite/4, 25
C	SallbackModule:handle_cast/2, 15		pwrite/5, 25
	SallbackModule:handle_msg/2, 15		read/3, 24
C	SallbackModule:handle_ssh_msg/2, 15		read/4, 24
C	SallbackModule:init/1,14		read_file/2, 23
C	SallbackModule:terminate/2,17		read_file/3, 23
C	ast/2, 11		read_file_info/2, 26
е	enter_loop/1, 12		
i	nit/1, 12		read_file_info/3, 26
r	eply/2, 12		read_link/2, 27
S	tart/4, 13		read_link/3, 27
S	tart_link/4,13		read_link_info/2, 27
ssh o	onnection		read_link_info/3, 27
			rename/3, 28
	djust_window/3, 19		rename/4, 28
	close/2, 19		start_channel/1,22
	exec/4, 19		start_channel/2,22
	exit_status/3, 20		start_channel/3,22
	reply_request/4, 20		stop_channel/1, 23
	send/3, 20		write/3, 25
	send/4, 20		write/4, 25
	send/5, 20		write_file/3, 23
	end_eof/2, 20		write_file/4, 23
	session_channel/2,21		write_file_info/3, 27
	session_channel/4, 21		write_file_info/4,27
	setenv/5, 21	ssh_	sftpd
	shell/2, 21		subsystem_spec/1, 29
S	subsystem/4, 21		
ssh_sf	Ĉtp	sta	rt/0
	-		ssh, 10

start/1 ssh, 10

start/4

ssh_channel, 13

start_channel/1 ssh_sftp, 22

start_channel/2 ssh_sftp, 22

start_channel/3 ssh_sftp, 22

start_link/4 ssh_channel, 13

stop/0 ssh, 10

stop_channel/1
ssh_sftp, 23

 $stop_daemon/1 \\ ssh$, 10

stop_daemon/2 ssh, 10

ssh, 10

 $stop_listener/2$ ssh, 10

subsystem/4
ssh_connection, 21

subsystem_spec/1 ssh_sftpd, 29

write/3 ssh_sftp, 25

write/4 ssh_sftp, 25

 $\begin{array}{c} {\tt write_file/3} \\ {\it ssh_sftp} \;, \, 23 \end{array}$

 $\begin{array}{c} {\tt write_file/4} \\ {\it ssh_sftp} \;, \, 23 \end{array}$

write_file_info/3 ssh_sftp, 27

write_file_info/4 ssh_sftp, 27